

# Silently Installing SynchronEyes™ Software Version 7.x



**Applies to:** SynchronEyes™ software version 7.x for the Windows® operating system

## Overview

This document provides instructions for silently installing SynchronEyes software version 7.x.

## Details

To silently install SynchronEyes software from a server, copy the contents of the installation CD to your server's hard disk. Take note of the path to the copied files, because you must type this path in the following procedure's commands.

You can then:

- silently install SynchronEyes software on a teacher's computer
- silently install SynchronEyes software on a student's computer
- silently install the SynchronEyes software Quiz Wizard

## NOTES

- Type commands exactly as they appear in the following procedures, including all spaces, slashes and punctuation.
- Don't attempt an MSI installation unless you're familiar with the commands.

## Silently Installing SynchronEyes Teacher-Station Software on a Teacher's Computer

Install and start SynchronEyes software on the teacher's computer before you install it on a student's computer. When you first install SynchronEyes teacher-station software on a teacher's computer, you define parameters that you will use when you install the software on a student's computer.

### To silently install SynchronEyes teacher-station software on a teacher's computer

1. Select **Start > Run**.  
The *Run* dialog box appears.
2. Type **cmd** and click **OK**.  
The *C:\WINDOWS\system32\cmd.exe* window appears.
3. Type **msiexec /i "*path to the .msi file*\SynchronEyes Teacher 7.0.msi" /qn** and press ENTER.

**NOTE:** The **SynchronEyes Teacher 7.0.msi** file is located in the CD's **TeacherSetup** folder.

The installation takes several seconds. When the installation is complete, a **SynchronEyes Teacher 7.0** icon appears on your desktop.

4. Double-click the **SynchronEyes Teacher 7.0** desktop icon.  
The *Teacher ID* dialog box appears.
5. Type a unique teacher ID, and then click **OK**.  
The *SynchronEyes Software Evaluation* dialog box opens.

6. Click the **Activate License** button. Type your registration information in the required fields, and then click **Next**.

SynchronEyes software starts.

**IMPORTANT**



Do not close SynchronEyes software on the teacher's computer until you install the software on all student computers.

## Silently Installing SynchronEyes Student-Station Software on a Student's Computer

**IMPORTANT**



Do not silently install SynchronEyes software on the first student computer.

Install the software from the CD on a student's computer and select your installation settings. When you install SynchronEyes software on the first student's computer, you create a **SynchronEyesClient.ini** file in the **C:\Program Files\SynchronEyes Student** folder. This file contains your customized installation settings. See the [SynchronEyes Classroom Management Software Installation Guide](#) for more information on installing SynchronEyes software on a student's computer (not silently).

You can then silently install SynchronEyes student-station software on the other students' computers, copy the **SynchronEyesClient.ini** file to the server, and ensure that all student computers have the same installation settings.

### To ensure that all student computers have the same installation settings

1. Follow the installation steps described in the next procedure to upgrade SynchronEyes student-station software on one student's computer.
2. Copy the **SynchronEyesClient.ini** file from the **C:\Program Files\SynchronEyes Student** folder, and then paste it in the **StudentSetup** folder on the server.

**NOTE:** The **StudentSetup** folder contains the **SynchronEyes Student 7.0.msi** file.

- When you customize installation settings, you automatically save the settings to the **SynchronEyesClient.ini** file. Copy the .ini file to the **StudentSetup** folder on the server to save the updated installation settings for all student computers.
- When you don't customize installation settings, copy the **SynchronEyesClient.ini** file to the **StudentSetup** folder on the server to save the installation settings from the previous installation for all student computers.
- When you customize installation settings but you don't copy the **SynchronEyesClient.ini** file to the **StudentSetup** folder on the server, you save the default installation settings from the first computer for all student computers.

### To silently install SynchronEyes student-station software on a student's computer

1. Select **Start > Run**.

The *Run* dialog box appears.

2. Type **cmd** and click **OK**.

The *C:\WINDOWS\system32\cmd.exe* window appears.

3. Type `msiexec /i "path to the msi file\SynchronEyes Student 7.0.msi" /qn` and press ENTER.

The installation takes several seconds. When the installation is complete, the computer restarts.

## Silently Installing the SynchronEyes Software Quiz Wizard

When you install SynchronEyes software on a teacher's computer, you automatically install the Quiz Wizard. However, you can also install a stand-alone version of the Quiz Wizard on a separate computer.

### To silently install the SynchronEyes software Quiz Wizard

1. Select **Start > Run**.

The *Run* dialog box appears.

2. Type **cmd** and click **OK**.

The *C:\WINDOWS\system32\cmd.exe* window appears.

3. Type `"path to the .exe file\SynchronEyesQuizSetup.exe" /s /v/qn` and press ENTER.

**NOTE:** The **SynchronEyesQuizSetup.exe** file is in the top level of the CD Contents.

The installation takes several seconds. When the installation is complete, a **Quiz Wizard** icon appears on the desktop.

**First Published:** May 14, 2007

**Last Updated:** January 30, 2008

**SMART Technologie**  
1207 – 11 Avenue SW, Suite 300  
Calgary, AB T3C 0M5  
CANADA



[www.smarttech.com/support](http://www.smarttech.com/support) [www.smarttech.com/contactsupport](http://www.smarttech.com/contactsupport)  
Support +1.403.228.5940 or Toll Free 1.866.518.6791 (Canada/U.S.)

© 2007–2008 SMART Technologies ULC. All rights reserved. SynchronEyes, smarttech and the SMART logo are trademarks or registered trademarks of SMART Technologies ULC in the U.S. and/or other countries. Windows is either a registered trademark or a trademark of Microsoft Corporation in the U.S. and/or other countries. All other third-party product and company names may be trademarks of their respective owners. Patents pending. Contents are subject to change without notice. 01/2008.