

Silently Installing SynchronEyes™ Software Version 6.x



Applies to: SynchronEyes™ software Version 6.x for the Windows® operating system

Overview

This document provides instructions for silently installing SynchronEyes software version 6.x.

Details

To silently install SynchronEyes software from a server, copy the contents of the installation CD to your server's hard disk. Take note of the path to the copied files, because you must type this path in the following procedure's commands.

You can then:

- silently install SynchronEyes software on a teacher's computer
- silently install SynchronEyes software on a student's computer
- silently install the SynchronEyes software Quiz Wizard

NOTES

- Type commands exactly as they appear in the following procedures, including all spaces, slashes and punctuation.
- Don't attempt an MSI installation unless you're familiar with the commands.

Silently Installing SynchronEyes Software on a Teacher's Computer

Install and start SynchronEyes software on the teacher's computer before you install it on a student's computer. When you first install SynchronEyes software on a teacher's computer, you define parameters that you will use when you install the software on a student's computer.

To silently install SynchronEyes software on a teacher's computer

1. Select **Start > Run**.
The *Run* dialog box appears.
2. Type **cmd** and click **OK**.
The *C:\WINDOWS\system32\cmd.exe* window appears.
3. If you are installing SynchronEyes software version 6.0, type **msiexec /i "path to the .msi file\SynchronEyes Teacher 6.0.msi" /qn** and press ENTER.

OR

If you are installing SynchronEyes software version 6.1, type **msiexec /i "path to the .msi file\SynchronEyes Teacher 6.1.msi" /qn** and press ENTER.

NOTE: The .msi file is located in the CD's **TeacherSetup** folder.

The installation takes several seconds. When the installation is complete, a **SynchronEyes Teacher** icon appears on your desktop.

4. Double-click the **SynchronEyes Teacher** icon.
The *Teacher ID* dialog box opens.

5. Type a unique teacher ID and click **OK**.

The *SynchronEyes Software Evaluation* dialog box opens.

6. Click the **Activate License** button. Type your registration information in the required fields, and then click **Next**.

SynchronEyes software starts. .

IMPORTANT



Do not close SynchronEyes software on the teacher's computer until you install the software on all student computers.

Silently Installing SynchronEyes Software on a Student's Computer

IMPORTANT



Do not silently install SynchronEyes software on the first student computer.

Install the software from the CD on a student computer and select your installation settings. When you install SynchronEyes software on the first student computer, you create a **SynchronEyesClient.ini** file in the **C:\Program Files\SynchronEyes Student** folder. This file contains your customized installation settings. See the [SynchronEyes Classroom Management Software User's Guide](#) for more information on installing SynchronEyes software on a student's computer (not silently).

You can then silently install SynchronEyes software on the other students' computers, copy or push the **SynchronEyesClient.ini** file to all other student computers, and ensure that all computers have the same installation settings.

To copy the SynchronEyesClient.ini file

After you install SynchronEyes software on one student's computer, copy the **SynchronEyesClient.ini** file from the **C:\Program Files\SynchronEyes Student** folder, and then paste it into the **StudentSetup** folder on the server. The **StudentSetup** folder contains the .msi file.

When you run the installation command detailed in the next procedure, the software's customized settings saved in the .ini file will be copied to each student's computer automatically. However, if you silently install SynchronEyes software on the other student's computers without copying the .ini file in this way, you will automatically select the software's default settings.

To silently install SynchronEyes software on a student's computer

1. Select **Start > Run**.

The *Run* dialog box appears.

2. Type **cmd** and click **OK**.

The *C:\WINDOWS\system32\cmd.exe* window appears.

3. If you are installing SynchronEyes software version 6.0, type **msiexec /i "path to the msi file\SynchronEyes Student 6.0.msi" /qn** and press ENTER.

OR

If you are installing SynchronEyes software version 6.1, type **msiexec /i "path to the msi file\SynchronEyes Student 6.1.msi" /qn** and press ENTER.

The installation takes several seconds. When the installation is complete, the computer restarts.

Silently Installing the SynchronEyes Software Quiz Wizard

When you install SynchronEyes software on a teacher's computer, you automatically install the Quiz Wizard. However, you can install a stand-alone version of the Quiz Wizard on a separate computer.

To silently install the SynchronEyes software Quiz Wizard

1. Select **Start > Run**.

The *Run* dialog box appears.

2. Type **cmd** and click **OK**.

The *C:\WINDOWS\system32\cmd.exe* window appears.

3. Type "**path to the .exe file/SynchronEyesQuizSetup.exe**" /s /v/qn and press ENTER.

NOTE: The **SynchronEyesQuizSetup.exe** file is in the top level of the CD Contents.

The installation takes several seconds. When the installation is complete, a **Quiz Wizard** icon appears on the desktop.

First Published: March 8, 2006

Last Updated: December 10, 2007

SMART Technologies
1207 – 11 Avenue SW, Suite 300
Calgary, AB T3C 0M5
CANADA

www.smarttech.com/support www.smarttech.com/contactsupport
Support +1.403.228.5940 or Toll Free 1.866.518.6791 (Canada/U.S.)

